

GoPro Color Grading LUTs

(Sample Pack)



In this sample pack, you will find 10 cinematic presets to get you started with color grading your Photos and Videos. They have been crafted by our videographers at Project GoPro and are optimized for GoPro and Drone content.

We have included different LUTs formats to cover most photo and video editing software, such as Adobe Photoshop (.CUBE), Adobe Premiere Pro (.CUBE), Adobe Lightroom (.XML), Final Cut Pro X (.CUBE), Davinci Resolve (.CUBE), and much more.

Install the presets in your editing software and start color grading right away.

Team ProjectGO


INSTALLATION GUIDE

- **Adobe:** [Premiere Pro](#), [Photoshop](#), [After Effects](#)
- **Final Cut Pro X (up to v10.3x):** [w/ mLUT](#)
- **Final Cut Pro X (from v10.4x):** [w/ FCP LUT loader](#) (*min 2:26*)
- **Others:** [DaVinci Resolve](#), [Assimilate Scratch](#), [Cyberlink PowerDirector](#), [Cyberlink ColorDirector](#), [ON1 Photo RAW](#)

- **Adobe Lightroom:**

Lightroom Classic & Adobe Camera Raw

First, in Lightroom, go to the Lightroom Preferences (NOT Catalog Preferences) and make sure that the "Store preset with this catalog" option is **not checked**.



Then, navigate to the Camera Raw > Settings folder and copy the .xmp preset files to that folder. Here is an alternate method of locating that folder:

- **Mac:** ~ / Library / Application Support / Adobe / CameraRaw / Settings
- **Windows:** C: \ ProgramData \ Adobe \ CameraRaw \ Settings

Alternately, you can access the folder with this method:

1. Open Lightroom CC (make sure it is updated to the new version)
2. Go to **Lightroom > Preferences**
3. Click the "Preset" section at the top
4. Click the "Show Lightroom Presets Folder"
5. Ignore the folder it highlights, and instead go up to the **Camera Raw** folder and open it
6. Open the **Settings** folder and copy your .xml presets files into this folder
7. Restart Photoshop or Lightroom Classic and the presets/profiles should be installed.

Lightroom CC

1. Open Lightroom CC and access the Presets panel.
2. Next, click on the "..." drop down and select **Import Presets**.
3. Navigate to the folder containing the .xml files and select it to import into Lightroom CC. Your profiles will then install and are ready to use.